



**diskDISK™**



*Copyright 1983*

**MISOSYS, Inc.**



**MISOSYS, Inc.**

TRS-80 MODEL I/III

CATALOG #L-35-211

**LOGICAL  
SYSTEMS  
INC.**

MILWAUKEE, WI

COPYRIGHT ©1983

Disk/DISK

VERSION #

DskDSK S/N 20174

ALL RIGHTS RESERVED

TRS-80 MODEL 4

CATALOG #L-35-212

**LOGICAL  
SYSTEMS  
INC.**

MILWAUKEE, WI

COPYRIGHT ©1983

LS-Disk/DISK

VERSION #

LS-DDSK S/N 20186

ALL RIGHTS RESERVED

# [LS-]diskDISK™ - Simulate a disk with a file

## Table of Contents

General Information . . . . .	1
Creating a diskDISK . . . . .	2
Setting up an existing diskDISK file. . . . .	4
Disabling a diskDISK. . . . .	6
Examples of diskDISK use. . . . .	6
DiskDISK file structure . . . . .	7
DiskDISK driver and linkage . . . . .	7
Warranty and Customer Support . . . . .	8

diskDISK™, LS-diskDISK™: Copyright © 1983 MISOSYS, Inc., All rights reserved.  
Published by MISOSYS, Inc., PO BOX 239, Sterling, VA 22170-0239.

The distribution and sale of this program is intended for the personal use of the original purchaser only and for use only on the computer system noted herein. Furthermore, copying, duplicating, selling, or otherwise distributing this product is expressly forbidden. In accepting this product, the purchaser recognizes and accepts this agreement. The purchaser is entitled to make as many working copies of this disk as is needed for his or her personal use.

LDOS is a trademark of MISOSYS, Inc.  
LS-DOS is a trademark of Logical Systems Inc.  
TRSDOS is a trademark of Tandy Corporation

## General Information

The diskDISK utility package allows the user to simulate a logical floppy disk drive by means of a disk file on a physical drive. This is useful for creating mirror image backups from a drive with larger storage capacity to a drive with lesser storage. It is also useful for partitioning a large disk volume (i.e. hard disk) into smaller regions. This effectively overcomes the limitation of 256 directory entries per "disk".

DiskDISK consists of two separate modules:

- DDFORM/CMD - a formatter program which initially creates a diskDISK;
- DD/CMD - a program which either sets up an existing diskDISK file as a drive, or disables an active diskDISK.

The files on the accompanying DATA diskette may be easily copied to your working SYSTEM disk by means of the DOS COPY utility. There may be a file named "README/TXT" on the disk. If so, this file will contain important information which may not appear in this printed documentation. You should read this file by issuing the command: LIST README.

## [LS-]diskDISK™ - Simulate a disk with a file

### Creating a diskDISK

The DDFORM utility creates a diskDISK file based on information given by you. You can create a diskDISK file from the DOS, from inside BASIC, or from within an applications program (in most cases). The syntax to create a diskDISK file is:

```
DDFORM [filespec (parm, parm, ... )]
```

filespec	This is the name of the diskDISK file to be created. Standard operating system rules regarding file names apply.
Type=t	't' is one of 1, 2, 5 or 8. This indicates the type of diskDISK to be created. The default is 5.
Sides=s	's' is either 1 or 2, indicating the number of "logical" sides to assign to the diskDISK file. The default is 1.
Density=d	where 'd' is either "D" for double density, or "S" for single. This is the "logical" density. The default is "D".
Cylinders=c	where 'c' is a value between 3 and 96. This indicates the number of "logical" cylinders to allocate within the diskDISK file. The defaults are 40 for type 5, and 77 for type 8.

SIDES and DENSITY have no meaning in regard to types 1 and 2.  
CYLINDERS must be specified for types 1 and 2.  
All parameters may be abbreviated to their first character.  
Items within "[]" are optional.

Thus, a typical format command is structured as:

```
DDFORM filespec (optional parameters)
```

The "filespec" entry is the destination file specification of the diskDISK file. If "filespec" is not specified, a prompt will appear asking for it. If sufficient disk space is not available, no diskDISK file will be created, and the diskDISK utility will abort, displaying the error message:

#### Disk Space Full

If a file already exists by that name, the utility will abort, displaying the error message:

#### File Already Exists

There are four optional parameters that can be used in creating a diskDISK: Type, Sides, Density, and Cylinders.



## **[LS-]diskDISK™ - Simulate a disk with a file**

TYPE is entered as either 1, 2, 5 or 8 (the default is 5), indicating the type of diskDISK. A type 1 diskDISK uses an optimized storage technique, allocating files in the smallest blocks as possible (1 sector per granule, 8 granules per cylinder). Using type 1, a file will only use the minimum disk space possible under the DOS. However, it is not possible to use a type 1 diskDISK as a system disk. The maximum size of a type 1 diskDISK is 192K. A type 2 diskDISK uses larger blocks, but can also be twice as large as type 1 (2 sectors per granule, 8 granules per cylinder). Types 5 and 8 refer to the type of floppy drive to simulate as a diskDISK (5" or 8").

SIDES is entered as a value of 1 or 2 (the default is 1), indicating the number of logical sides (1 or 2) to allocate in a diskDISK file.

DENSITY is entered as "D" for double density, or "S" for single density. This refers to the "logical" density within the diskDISK file. The default is double density.

CYLINDERS is entered as a value between 3 and 96 indicating the number of "logical" cylinders to allocate within the diskDISK file. The default value is 40 for 5" drive types, or 77 for 8" drive types.

SIDES and DENSITY may not be used with types 1 and 2. CYLINDERS must be specified if type is 1 or 2. All parameter names may be abbreviated to their first character. If no parameters are entered when creating a diskDISK, then prompts will be displayed requesting the parameter values. Pressing <ENTER> in response to a prompt will indicate use of the default value for that parameter. Invalid responses will cause reprompting until valid values are entered. If one or more of the parameters are entered on the command line, no prompts will appear, and the default values for parameters not entered will be used. Pressing <BREAK> to any prompt will cause the create utility to abort.

### **Possible error messages from DDFORM**

**Requested file would require more than 12 extents !** - This error message will occur if the diskDISK file to be created would be broken into an excessive number of non-contiguous pieces. This is normally indicative of a diskette that is very fragmented. Usually a BACKUP-BY-CLASS to a empty, formatted diskette will reduce this fragmentation.

**Parameter Error** - One or more of the parameters entered when invoking DDFORM were either incorrectly specified or misspelled.

**File Already Exists** - The filename specified is already in use on the specified destination drive.

## [LS-]diskDISK™ - Simulate a disk with a file

### Setting up an existing diskDISK file

Once you have created diskDISKs, you use the DD utility to make the disk drive emulation accessible from a drive slot. DD is invoked with the syntax:

```
DD :drivespec filespec (DISABLE)
```

```
drivespec      The logical drive slot in which to install the  
                diskDISK file. The colon is optional.
```

```
filespec       Specification of the diskDISK file to installed.
```

```
Disable        Disables an existing diskDISK file.
```

```
All parameters may be abbreviated to their first character
```

The diskDISK setup utility installs a driver program into high memory (or low memory in LS-DOS 6.x, if available) which interfaces the diskDISK file with the system. In addition to the driver, one linkage program is installed for every diskDISK drive used. A diskDISK may be re-installed using the same logical drive number as often as desired. No additional memory will be used on subsequent installations. Therefore, it is possible to set-up a diskDISK, BACKUP files to it, set-up another, BACKUP files to it, etc. It is also possible to SYSGEN with an active diskDISK, but the diskDISK file must be present on the same drive it was SYSGENed on, and in EXACTLY the same physical position, or disastrous results will occur.

THE "drivespec" entry is the logical drive number (1-7) to use as the diskDISK. The colon is optional. If the drivespec is not specified, or is invalid, a prompt will appear asking for it.

The "filespec" entry is the file specification of the diskDISK file. The default extension for diskDISK files is "/DSK". If "filespec" is not specified, a prompt will appear asking for the filespec. Obviously, "filespec" cannot be on the same drive number as "drivespec". If this should happen accidentally, the message:

**diskDISK drivespec identical to FILE drivespec**

will be displayed, and the assignment will be aborted.

Most commands available from the DOS can be used on the diskDISK drive. Do not use any form of the REMOVE, PURGE or KILL commands on a file that is serving as an active diskDISK drive. Disable the diskDISK drive prior to removing the file.

Also, do NOT attempt to "COPY filespec1 to filespec2", where "filespec2" is an active diskDISK file. This is not the proper method of swapping active diskDISKs. LS-DOS 6.x keeps active diskDISK files open, so the error "File Already Open" may be displayed on certain functions attempting to access the file.

Generally speaking, don't do anything which will modify an active diskDISK file, or a logical drive slot (DCT) that is currently assigned to a diskDISK.

## **[LS-]diskDISK™ - Simulate a disk with a file**

DiskDISKs can be used as system disks within certain limits:

1. The diskDISK file to be used as a system disk cannot be a type 1 diskDISK. Only type 2, 5, or 8 can be used as system disks. Type 2 will provide for the most efficient storage of the operating system.
2. The diskDISK to be used as a system disk cannot be located on the physical drive or diskDISK that is currently serving as drive 0 (the system drive). Also, no currently active (installed) diskDISKs may be located on the current drive 0 or on the destination disk or diskDISK when executing ANY form of the SYSTEM (SYSTEM=d) command.

### **Possible error messages from DD**

**Parameter Error** - One or more of the parameters entered when invoking DD were either incorrectly specified or misspelled.

**Can't install diskDISK, memory not available** - An attempt was made to alter a diskDISK configuration that would require additional memory, and this additional memory is not available. This will occur if an attempt is made to install an additional diskDISK from inside of BASIC, for example. However, swapping of diskDISK files in already installed drive slots is allowed.

**Drive not a diskDISK** - The DD disable parameter was specified, and the indicated drive slot was not an active diskDISK.

**File Contains too many extents** - Any diskDISK file is limited to a maximum of twelve directory extents. To this end, DDFORM will not allow creation of a diskDISK with more. If a diskDISK file is copied from one diskette to another, it is possible that the destination file will have more than twelve extents. To avoid this, copy large diskDISK files only to relatively "empty" diskettes, and check the number of extents on the destination file with the "DIR :d (A)" command.

**Unable to reclaim both driver and linkage memory** - This is a non-fatal error. It simply indicates that a disable command was issued, and DD could not totally free memory. There are two major causes for this. First, there was more than one diskDISK active. The driver cannot be removed because it must service the other diskDISK. Second, some program, driver or filter used after DD is using memory. DD cannot release its memory because it has been "trapped" by this second program. The best way to recover this memory is to re-boot.

**Illegal diskDISK file** - The file specified for installation with DD was not a diskDISK file created by DDFORM.

**diskDISK drivespec identical to FILE drivespec** - An attempt was made to install a diskDISK file into a logical drive slot occupied by the media or diskDISK containing the diskDISK to be installed.

## [LS-]diskDISK™ - Simulate a disk with a file

### Disabling a diskDISK

The syntax to DISABLE a diskDISK is:

```
DD :drivespec (DISABLE)
```

"D" may also be used as an abbreviation for DISABLE. If "drivespec" is omitted, a prompt will appear asking for it. Disabling a diskDISK drive does not affect the contents of a diskDISK file. The main purpose of disabling the diskDISK is to reclaim memory used by the driver/linkage, and close the diskDISK file. If it is not desired to reclaim the memory used by the linkage, simply use the DOS command "SYSTEM (DRIVE=d,DISABLE)". Sometimes it is not possible to reclaim the memory used by the driver. This may be the case if some module was installed after the diskDISK, or additional diskDISKs are operational.

### Examples of diskDISK use

To create a diskDISK file "DRIVE5/DSK:3", with 30 cylinders and optimized allocation (Type 1):

```
DDFORM DRIVE5:3 (C=30,T=1)
```

Note that a default extension of "/DSK" will be added to the filespec given unless the filespec contains an extension, or the filespec contains a null extension.

To install the diskDISK as logical drive 5:

```
DD 5 DRIVE5:3
```

Again, note that the default extension is "/DSK". The syntax for creating a 5" double-sided, double density diskDISK file named DDFILE is:

```
DDFORM DDFILE/ (S=2)
```

To install it as logical drive 7, type:

```
DD :7 DDFILE/
```

Note that in both cases, a "/" with nothing after it was used to force a filename with no extension.

To create a mirror-image of a floppy disk on a drive of larger capacity, simply create a diskDISK that exactly matches the desired diskette in cylinders, density and number of sides. Next, install the diskDISK with DD. Now, simply perform a mirror-image backup from the floppy disk to the diskDISK.

This diskDISK can now be used to make floppy disk copies (through mirror-image backup, or another suitable utility), or for almost any other purpose.

For example, let's say that a 5", single density, 35 cylinder diskette is to be placed on a Hard Disk system, which is set up on drive 5. Drive slot 7 is available. First, create the diskDISK with:



## [LS-]diskDISK™ - Simulate a disk with a file

DDFORM DISKDISK:5 (C=35,D="S")

Note that the defaults of 5" and 1 side will be used, and the extension "/DSK" will be assigned. Second, install the diskDISK with the command:

DD :7 diskDISK

This will install the file in logical drive slot 7. Now, assuming that drive 3 is a floppy disk, the DOS command:

BACKUP :3 :7

would make a mirror-image copy of the floppy disk in drive 3. Note also that if DDFORM is entered without giving any parameters, all necessary information will be prompted for, as shown in the following examples:

```
DDFORM - diskDISK Creation Utility
Copyright (C) 1983 by MISOSYS, Inc.
Version x.x.xx
Enter Filespec : diskdisk:7
Enter Disk Type {1, 2, 5, or 8 - default = 5} : 1
Enter Cylinders {Note : 1 Cyl = 2.00K} : 50
diskDISK File Created

Enter Filespec : diskdis2:7
Enter Disk Type {1, 2, 5, or 8 - default = 5} : 5
Enter Sides {Default = 1 side} : 2
Enter Density {Default = double} :
Enter Cylinders {Note : 1 Cyl = 9.00K} : 12
diskDISK File Created
```

If only the <ENTER> key is pressed in response to a prompt, the default value for that parameter will be assumed. If there is no default value, the prompt will re-appear.

### DiskDISK file structure

The diskDISK file contains BOOT/SYS and DIR/SYS, just as any floppy does. It also contains an additional sector not accessible on a logical drive basis. Relative record X'0000' of the diskDISK file contains an ID field to distinguish it from a non-diskDISK file. It also contains DCT slot information which will be used to re-install this diskDISK next time.

### DiskDISK driver and linkage

The DD installation utility will attempt to install a driver program (\$DD), and a linkage module (\$DL), in high memory (or the low memory driver zone for LS-DOS 6.x, if room is available). The \$DD driver will use the DCT for all cylinder and sector calculation. Therefore, it will only be installed once - even if there are multiple diskDISKs. However one \$DL module will be installed for every diskDISK used. The driver removal program will reclaim memory IF POSSIBLE. This is a BIG if! If there is ONLY one diskDISK active, and nothing was installed underneath it (if installed in high memory), or above it (if installed in the driver area on LS-DOS 6.x), then the memory will be reclaimed. If there is more than one diskDISK active, the driver WILL NOT be disabled, because it is necessary to service the other diskDISKs.

### Warranty

This software program(s) is warranted to perform as documented when used on the specified hardware operating under the specified disk operating system as shown on the accompanying documentation. If within 90 days of the date of purchase the program is found to be defective due to a bug in the code, the publisher will, upon request, provide a patch to correct the bug or will update the program diskette with a corrected copy within a reasonable time period after return of the program diskette to the publisher. If within 90 days of the date of purchase the documentation proves defective due to missing pages, the publisher will provide substitutes for the missing pages upon request.

The publisher shall have no liability or responsibility to the purchaser or any other person, company, or entity with respect to any liability, loss, or damage caused or alleged to have been caused by this product, including but not limited to any interruption of service, loss of business and anticipatory profits, or consequential damages resulting from the operation or use of this program.

### Customer Support

Customer service information on this product may be acquired by contacting MISOSYS, Inc., at the following address:

MISOSYS, Inc.  
P.O. Box 239  
Sterling, Virginia 22170-0239  
703-450-4181