

# QUALITY SOFTWARE DISTRIBUTORS

---



**Breeze/QSD, Inc.**  
11500 Stemmons Exp., Suite 125  
Dallas, Texas 75229

\*\*\*\*\*  
I/III File Tranfer Utility  
by Kim Watt  
Breeze/QSD, Inc.  
\*\*\*\*\*  
Documentation  
\*\*\*\*\*

You have just purchased a highly sophisticated solution to diskette duplicating and distribution problems. You will find two diskettes enclosed. One is marked "I/III Transfer Utility MASTER", and the other "I/III Transfer Utility COPY UTILITY".

## Setting up a master diskette:

Insert the COPY UTILITY disk in Drive 0 in your Mod III and press the reset button. Remove this disk, and insert the MASTER in drive 0. Insert a blank formatted disk in drive 1. Copy the disk from 0 to 1 following instructions in the duplicating section. Go there NOW and read how to make a copy.

Ok, now that you are back and have a BACKUP, PUT AWAY THE MASTER. You no longer need it for this procedure. You may now boot your Mod III TRSDOS in drive 0, and get a directory of the disk you just made in drive 1. Copy all the Mod III programs you want to distribute onto that diskette. The protection level and passwords will be copied as you have them set. Only visible files will be transferred to the end users diskette. You may now insert the disk into drive 1 of your Mod I and get a directory. Copy all the Mod I programs you want to distribute onto the disk. If you have the same version of a program that runs in both machines, be sure to copy over in both the Mod's I and III. You now have a master disk that you can duplicate and distribute. Put a write protect tab and label on it. This disk will now boot in EITHER a Mod I OR III.

## Duplication:

Insert the COPY UTILITY diskette into drive 0 of a Mod III and press the reset button. After a short loading delay, the heading will be displayed. A memory test is performed to assure you that the buffer area is fully usable. REMOVE the COPY UTILITY, as it is no longer needed, and insert your Master that you made by the above procedure. You are then asked to supply the step speed at which the program is to run. Answer with the value of your slowest drive that is being used. Now you may enter the number of copies that you wish to make in this run. Answer with 1-255. The track count of the master disk is prompted. The normal diskette will contain 40 tracks, which is the default value. This option has been left in for your special applications.



**Breeze/QSD, Inc.**  
11500 Stemmons Exp., Suite 125  
Dallas, Texas 75229

Next you may specify if you wish a byte for byte verify done on the copies. It is suggested to use it to assure you of high reliability. You are then prompted for the source drive, which would normally be 0. Then drives 1-3 are prompted if you wish them included as destination drives. Any or all may be included. All of these parameters can be viewed at the top of the display. The diskette mounting will then be prompted as it is required. When the copy has completed, each destination drive status will be reported, and the count of good disks will be updated.

The verify procedure of this program is quite thorough, and may produce some apparant bad copies. If they fail after 2 attempts, do not use that diskette in this run.

#### Comments / Suggestions / Modifications

Custom modifications to the program is available. If you need 75K Mod III data space, and 25K Mod I, for example, and adjustment will be made at the rate of \$100 per master disk. By owning this package, you also have the following service available to you. If you have a single machine language program that runs on both the Mod I and III (even if different versions), and would like a disk that can boot into BOTH the Mod I and III, and requires no outside operating system, then we can help you. Just mail the version(s) of the program that you want to Breeze/QSD along with \$100, and we will return you with a MASTER disk that you can duplicate with your COPY UTILITY. Additional features, such as a SAVE/RESTORE GAME feature can be added by us at the rate of \$100 per hour.

Breeze/QSD, Inc.  
11500 Stemmons Fwy.  
Suite 125  
Dallas, Texas 75229  
(214) 484-9428  
(214) 484-2976